


How to Get My Valid MAC Address for License File

To locate the HostID (MAC Address) of your PC, open a Command Prompt Window (cmd.exe) and type `ipconfig/all`



Then search for **Ethernet adapter Ethernet** or **Wireless LAN adapter (Wi-Fi)**.

```
Windows IP Configuration

Host Name . . . . . : my-PC-Name
Primary Dns Suffix . . . . . :
Node Type . . . . . : Hybrid
IP Routing Enabled. . . . . : No
WINS Proxy Enabled. . . . . : No

Ethernet adapter Ethernet:

Connection-specific DNS Suffix . . :
Description . . . . . : Intel(R) Ethernet Connection (5) I219-LM
Physical Address. . . . . : 00-E7-CF-A0-CD-06
Dhcp Enabled. . . . . : Yes
Autoconfiguration Enabled . . . . : Yes
IPv4 Address. . . . . : 180.115.12.1(Preferred)
Subnet Mask . . . . . : 255.255.255.0
Lease Obtained. . . . . : Thursday, November 14, 2019 8:35:51 AM
Lease Expires . . . . . : Saturday, December 27, 2155 4:14:05 PM
Default Gateway . . . . . : 180.115.11.1
Dhcp Server . . . . . : 180.151.12.1
DNS Servers . . . . . : 8.8.8.8
                        8.8.8.8
NetBIOS over Tcpi. . . . . : Enabled

Wireless LAN adapter Wi-Fi:

Media State . . . . . : Media disconnected
Connection-specific DNS Suffix . . :
Description . . . . . : Intel(R) Dual Band Wireless-AC 8265
Physical Address. . . . . : 00-E3-A7-2C-3B-AF
Dhcp Enabled. . . . . : Yes
Autoconfiguration Enabled . . . . : Yes
```

The HostID will be a 12-digit alpha numerical code (e.g. 00-E7-CF-A0-CD-06).
FlowCAD recommends the MAC Address for **Ethernet adapter Ethernet**. If no Ethernet adapter is available please use the MAC Address for **Wireless LAN adapter Wi-Fi**.

Please Note

Any other network adapters are not supported by FlexLM License Manager!

Questions

For questions please contact FlowCAD Support at +49 89 45637-777.